

Console Messages ESY0070I - ESY0079W

Message	Explanation	Action
ESY0070I - CA SYSTEM ADAPTER DETECTED	During initialisation, the Computer Associates System Adapter was found to be active.	None. However, check to see that the CA-Dynam/D API DYNACC. PHASE is accessible in the libraries specified in the LIBDEF PHASE SEARCH JCS statement.
ESY0071W - MESSAGE QUEUE LENGTH EXCEEDED - MESSAGES LOST	The VTAM incore message buffer has been filled. The startup parameter 'VTAMQLEN=' determines its length. The default is 100 (k).	Change value of VTAMQLEN and restart Entire System Server.
ESY0072W - OPEN FOR VTAM PRINTER ACB FAILED (ERROR=:1:)	An attempt to open the VTAM ACB whose name was specified in the startup parameter 'SPOOLACB=' has failed. Common errors are: 088 - Application name is already active. 090 - The application was not defined or is not active. Every minute, another attempt will be made. If the open is successful, the message ESY0012I will appear.	Contact your VTAM systems programmer.
ESY0073W Invalid command.	An invalid operator command was entered.	Correct it.
ESY0074W - NATURAL-SUB-TASK - SYSOUT ALLOCATION FAILED	An attempt to allocate a sysout dataset to contain output from Natural programs failed.	Please check job control of Entire System Server.
ESY0076W - NATURAL SUBTASK PARAMETER ERROR	A parameter passed to the NATURAL-SUB-TASK was in error.	Correct parameter error and retry.
ESY0077W - CANNOT LOAD NATURAL MODULE	The specified NATURAL-SUB-TASK module could not be loaded.	Check startup parameter NATMOD and the load libraries.
ESY0078W - GETMAIN ERROR	Storage requested via GETMAIN/GETVIS failed.	Run Entire System Server in a task with more memory.
ESY0079W - SECURITY CLASS OPERCMDS NOT DEFINED	The security class OPERCMDS is not defined to your external security system (RACF/ACF2/TSS etc).	Contact your systems programmer.